C06HDF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

C06HDF computes the discrete quarter-wave Fourier cosine transforms of m sequences of real data values. This routine is designed to be particularly efficient on vector processors.

2 Specification

SUBROUTINE CO6HDF(DIRECT, M, N, X, INIT, TRIG, WORK, IFAIL)

INTEGER M, N, IFAIL

real X(M*N), TRIG(2*N), WORK(M*N)

CHARACTER*1 DIRECT, INIT

3 Description

Given m sequences of n real data values x_j^p , for $j=0,1,\ldots,n-1$; $p=1,2,\ldots,m$, this routine simultaneously calculates the quarter-wave Fourier cosine transforms of all the sequences defined by:

$$\hat{x}_{k}^{p} = \frac{1}{\sqrt{n}} \left\{ \frac{1}{2} x_{0}^{p} + \sum_{j=1}^{n-1} x_{j}^{p} \times \cos\left(j(2k-1)\frac{\pi}{2n}\right) \right\}, \quad \text{if DIRECT} = \text{'F' or 'f'},$$

or its inverse

$$x_k^p = \frac{2}{\sqrt{n}} \sum_{i=0}^{n-1} \hat{x}_j^p \times \cos\left((2j-1)k\frac{\pi}{2n}\right), \quad \text{if DIRECT} = \text{'B'} \text{ or 'b'},$$

for $k = 0, 1, \dots, n - 1$; $p = 1, 2, \dots, m$.

(Note the scale factor $\frac{1}{\sqrt{n}}$ in this definition.)

A call of the routine with DIRECT = 'F' followed by a call with DIRECT = 'B' will restore the original data.

The transform calculated by this routine can be used to solve Poisson's equation when the derivative of the solution is specified at the left boundary, and the solution is specified at the right boundary (Swarztrauber [2]). (See the Chapter Introduction.)

The routine uses a variant of the fast Fourier transform (FFT) algorithm (Brigham [1]) known as the Stockham self-sorting algorithm, described in Temperton [4], together with pre- and post-processing stages described in Swarztrauber [3]. Special coding is provided for the factors 2, 3, 4, 5 and 6. This routine is designed to be particularly efficient on vector processors, and it becomes especially fast as m, the number of transforms to be computed in parallel, increases.

4 References

- [1] Brigham E O (1973) The Fast Fourier Transform Prentice-Hall
- [2] Swarztrauber P N (1977) The methods of cyclic reduction, Fourier analysis and the FACR algorithm for the discrete solution of Poisson's equation on a rectangle SIAM Rev. 19 (3) 490–501
- [3] Swarztrauber P N (1982) Vectorizing the FFT's Parallel Computation (ed G Rodrique) Academic Press 51–83
- [4] Temperton C (1983) Fast mixed-radix real Fourier transforms J. Comput. Phys. 52 340–350

[NP3390/19/pdf] C06HDF.1

5 Parameters

1: DIRECT — CHARACTER*1

Input

On entry: if the Forward transform as defined in Section 3 is to be computed, then DIRECT must be set equal to 'F'. If the Backward transform is to be computed, that is the inverse, then DIRECT must be set equal to 'B'.

Constraint: DIRECT = 'F' or 'B'.

2: M — INTEGER

Input

On entry: the number of sequences to be transformed, m.

Constraint: $M \geq 1$.

3: N — INTEGER

Input

On entry: the number of real values in each sequence, n.

Constraint: $N \ge 1$.

4: X(M*N) - real array

Input/Output

On entry: the data must be stored in X as if in a two-dimensional array of dimension (1:M,0:N-1); each of the m sequences is stored in a **row** of the array. In other words, if the data values of the pth sequence to be transformed are denoted by x_j^p , for $j=0,1,\ldots,n-1$; $p=1,2,\ldots,m$, then the mn elements of the array X must contain the values

$$x_0^1, x_0^2, \dots, x_0^m, \ x_1^1, x_1^2, \dots, x_1^m, \dots, \ x_{n-1}^1, x_{n-1}^2, \dots, x_{n-1}^m.$$

On exit: the m quarter-wave cosine transforms stored as if in a two-dimensional array of dimension (1:M,0:N-1). Each of the m transforms is stored in a **row** of the array, overwriting the corresponding original sequence. If the n components of the pth quarter-wave cosine transform are denoted by \hat{x}_k^p , for $k = 0, 1, \ldots, n-1$; $p = 1, 2, \ldots, m$, then the mn elements of the array X contain the values

$$\hat{x}_0^1, \hat{x}_0^2, \dots, \hat{x}_0^m, \ \hat{x}_1^1, \hat{x}_1^2, \dots, \hat{x}_1^m, \dots, \ \hat{x}_{n-1}^1, \hat{x}_{n-1}^2, \dots, \hat{x}_{n-1}^m.$$

5: INIT — CHARACTER*1

Input

On entry: if the trigonometric coefficients required to compute the transforms are to be calculated by the routine and stored in the array TRIG, then INIT must be set equal to 'I' (Initial call).

If INIT contains 'S' (Subsequent call), then the routine assumes that trigonometric coefficients for the specified value of n are supplied in the array TRIG, having been calculated in a previous call to one of C06HAF, C06HBF, C06HCF or C06HDF.

If INIT contains 'R' (Restart), then the routine assumes that trigonometric coefficients for the particular value of n are supplied in the array TRIG, but does not check that C06HAF, C06HBF, C06HCF or C06HDF have previously been called. This option allows the TRIG array to be stored in an external file, read in and re-used without the need for a call with INIT equal to 'I'. The routine carries out a simple test to check that the current value of n is consistent with the array TRIG.

Constraint: INIT = 'I', 'S' or 'R'.

6: TRIG(2*N) - real array

Input/Output

On entry: if INIT = 'S' or 'R', TRIG must contain the required coefficients calculated in a previous call of the routine. Otherwise TRIG need not be set.

On exit: TRIG contains the required coefficients (computed by the routine if INIT = 'I').

7: WORK(M*N) — real array

Work space

C06HDF.2 [NP3390/19/pdf]

8: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, M < 1.

IFAIL = 2

On entry, N < 1.

IFAIL = 3

On entry, INIT is not one of 'I', 'S' or 'R'.

IFAIL = 4

Not used at this Mark.

IFAIL = 5

On entry, INIT =, 'S' or 'R', but the array TRIG and the current value of N are inconsistent.

IFAIL = 6

On entry, DIRECT is not one of 'F' or 'B'.

IFAIL = 7

An unexpected error has occurred in an internal call. Check all subroutine calls and array dimensions. Seek expert help.

7 Accuracy

Some indication of accuracy can be obtained by performing a subsequent inverse transform and comparing the results with the original sequence (in exact arithmetic they would be identical).

8 Further Comments

The time taken by the routine is approximately proportional to $nm \times \log n$, but also depends on the factors of n. The routine is fastest if the only prime factors of n are 2, 3 and 5, and is particularly slow if n is a large prime, or has large prime factors.

9 Example

This program reads in sequences of real data values and prints their quarter-wave cosine transforms as computed by C06HDF with DIRECT = 'F'. It then calls the routine again with DIRECT = or 'B' and prints the results which may be compared with the original data.

[NP3390/19/pdf] C06HDF.3

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
CO6HDF Example Program Text
   Mark 14 Revised. NAG Copyright 1989.
    .. Parameters ..
                     NIN, NOUT
   INTEGER
   PARAMETER
                     (NIN=5,NOUT=6)
   INTEGER
                    MMAX, NMAX
                    (MMAX=5,NMAX=20)
   PARAMETER
    .. Local Scalars ..
   INTEGER
                    I, IFAIL, J, M, N
    .. Local Arrays ..
   real
                     TRIG(2*NMAX), WORK(MMAX*NMAX), X(NMAX*MMAX)
    .. External Subroutines ..
   EXTERNAL
                     C06HDF
    .. Executable Statements ...
   WRITE (NOUT,*) 'CO6HDF Example Program Results'
   Skip heading in data file
   READ (NIN,*)
20 READ (NIN, *, END=120) M, N
   IF (M.LE.MMAX .AND. N.LE.NMAX) THEN
      DO 40 J = 1, M
          READ (NIN,*) (X(I*M+J),I=0,N-1)
40
      CONTINUE
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Original data values'
      WRITE (NOUT,*)
      DO 60 J = 1, M
          WRITE (NOUT,99999) (X(I*M+J),I=0,N-1)
 60
      CONTINUE
       IFAIL = 0
       -- Compute transform
       CALL CO6HDF('Forward', M, N, X, 'Initial', TRIG, WORK, IFAIL)
      WRITE (NOUT,*)
      WRITE (NOUT,*)
         'Discrete quarter-wave Fourier cosine transforms'
      WRITE (NOUT,*)
      DO 80 J = 1, M
          WRITE (NOUT, 99999) (X(I*M+J), I=0, N-1)
80
      CONTINUE
       -- Compute inverse transform
       CALL CO6HDF('Backward', M, N, X, 'Subsequent', TRIG, WORK, IFAIL)
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Original data as restored by inverse transform'
      WRITE (NOUT,*)
      DO 100 J = 1, M
          WRITE (NOUT,99999) (X(I*M+J),I=0,N-1)
100
      CONTINUE
      GO TO 20
      WRITE (NOUT,*) 'Invalid value of M or N'
   END IF
```

C06HDF.4 [NP3390/19/pdf]

```
120 STOP
*
99999 FORMAT (6X,7F10.4)
END
```

9.2 Program Data

```
C06HDF Example Program Data
3 6: Number of sequences, M, and number of values in each sequence, N
0.3854 0.6772 0.1138 0.6751 0.6362 0.1424: X, sequence 1
0.5417 0.2983 0.1181 0.7255 0.8638 0.8723: X, sequence 2
0.9172 0.0644 0.6037 0.6430 0.0428 0.4815: X, sequence 3
```

9.3 Program Results

CO6HDF Example Program Results

Original data values

0.3854	0.6772	0.1138	0.6751	0.6362	0.1424
0.5417	0.2983	0.1181	0.7255	0.8638	0.8723
0.9172	0.0644	0.6037	0.6430	0.0428	0.4815

Discrete quarter-wave Fourier cosine transforms

Original data as restored by inverse transform $% \left(t\right) =\left(t\right) +\left(t\right) +\left($

0.3854	0.6772	0.1138	0.6751	0.6362	0.1424
0.5417	0.2983	0.1181	0.7255	0.8638	0.8723
0.9172	0.0644	0.6037	0.6430	0.0428	0.4815

[NP3390/19/pdf] C06HDF.5 (last)