

NAG Fortran Library Routine Document

G05LJF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G05LJF generates a vector of pseudo-random numbers from a (negative) exponential distribution with mean a .

2 Specification

```
SUBROUTINE G05LJF(A, N, X, IGEN, ISEED, IFAIL)
INTEGER          N, IGEN, ISEED(4), IFAIL
real           A, X(*)
```

3 Description

The exponential distribution has PDF (probability density function):

$$f(x) = \frac{1}{a}e^{-x/a} \quad \text{if } x > 0,$$

$$f(x) = 0 \quad \text{otherwise.}$$

The routine returns the values

$$x_i = -a \ln y_i$$

where y_i are the next n numbers generated by a uniform (0,1) generator.

One of the initialisation routines G05KBF (for a repeatable sequence if computed sequentially) or G05KCF (for a non-repeatable sequence) must be called prior to the first call to G05LJF.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison-Wesley

Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin

5 Parameters

- | | | |
|----|---|---------------|
| 1: | A – real | <i>Input</i> |
| | <i>On entry:</i> the mean, a , of the distribution.
<i>Constraint:</i> $A > 0.0$. | |
| 2: | N – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the number, n , of pseudo-random numbers to be generated.
<i>Constraint:</i> $N \geq 0$. | |
| 3: | $X(*)$ – real array | <i>Output</i> |
| | Note: the dimension of the array X must be at least $\max(1, N)$.
<i>On exit:</i> the n pseudo-random numbers from the specified exponential distribution. | |

- 4: IGEN – INTEGER *Input*
On entry: must contain the identification number for the generator to be used to return a pseudo-random number and should remain unchanged following initialisation by a prior call to one of the routines G05KBF or G05KCF.
- 5: ISEED(4) – INTEGER array *Input/Output*
On entry: contains values which define the current state of the selected generator.
On exit: contains updated values defining the new state of the selected generator.
- 6: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $A \leq 0.0$.

IFAIL = 2

On entry, $N < 0$.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

The example program prints five pseudo-random numbers from an exponential distribution with mean 1.0, generated by a single call to G05LJF, after initialisation by G05KBF.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      G05LJF Example Program Text
*      Mark 20 Release. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER          NOUT, M
      PARAMETER       (NOUT=6, M=5)
*      .. Local Scalars ..
      INTEGER          IFAIL, IGEN
```

```
*      .. Local Arrays ..
      real                X(M)
      INTEGER            ISEED(4)
*      .. External Subroutines ..
      EXTERNAL          G05KBF, G05LJF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G05LJF Example Program Results'
      WRITE (NOUT,*)
*      Initialise the seed to a repeatable sequence
      ISEED(1) = 1762543
      ISEED(2) = 9324783
      ISEED(3) = 42344
      ISEED(4) = 742355
*      IGEN identifies the stream.
      IGEN = 1
      CALL G05KBF(IGEN,ISEED)
*
      IFAIL = 0
      CALL G05LJF(1.0e0,M,X,IGEN,ISEED,IFAIL)
*
      WRITE (NOUT,99999) X
      STOP
*
99999  FORMAT (1X,F10.4)
      END
```

9.2 Program Data

None.

9.3 Program Results

G05LJF Example Program Results

```
2.4155
0.0503
0.9004
0.2968
0.0515
```
