C06BAF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

C06BAF accelerates the convergence of a given convergent sequence to its limit.

2 Specification

SUBROUTINE CO6BAF(SEQN, NCALL, RESULT, ABSERR, WORK, IWORK, IFAIL)

INTEGER NCALL, IWORK, IFAIL

real SEQN, RESULT, ABSERR, WORK(IWORK)

3 Description

The routine performs Shanks' transformation on a given sequence of real values by means of the Epsilon algorithm of Wynn [2]. A (possibly unreliable) estimate of the absolute error is also given.

The routine must be called repetitively, once for each new term in the sequence.

4 References

- [1] Shanks D (1955) Nonlinear transformations of divergent and slowly convergent sequences J. Math. Phys. 34 1–42
- [2] Wynn P (1956) On a device for computing the $e_m(S_n)$ transformation Math. Tables Aids Comput. 10 91–96

5 Parameters

1: SEQN-real Input

On entry: the next term of the sequence to be considered.

2: NCALL — INTEGER Input/Output

On entry: on the first call NCALL must be set to 0. Thereafter NCALL must not be changed between calls.

On exit: the number of terms in the sequence that have been considered.

 $egin{aligned} ext{3:} & ext{RESULT} - real \end{aligned} \qquad \qquad Output$

On exit: the estimate of the limit of the sequence. For the first two calls, RESULT = SEQN.

4: ABSERR — real Output

On exit: an estimate of the absolute error in RESULT. For the first three calls, ABSERR is set to a large machine-dependent constant.

5: WORK(IWORK) - real array Workspace

Used as workspace, but must not be changed between calls.

6: IWORK — INTEGER Input

On entry: the dimension of the array WORK as declared in the (sub)program from which C06BAF is called.

Suggested value: (maximum number of terms in the sequence) +6. See Section 8.2.

Constraint: IWORK ≥ 7 .

[NP3390/19/pdf] C06BAF.1

7: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, NCALL < 0.

IFAIL = 2

On entry, IWORK < 7.

7 Accuracy

The accuracy of the absolute error estimate ABSERR varies considerably with the type of sequence to which the routine is applied. In general it is better when applied to oscillating sequences than to monotonic sequences where it may be a severe underestimate.

8 Further Comments

8.1 Timing

The time taken by the routine is approximately proportional to the final value of NCALL.

8.2 Choice of IWORK

For long sequences, a 'window' of the last n values can be used instead of all the terms of the sequence. Tests on a variety of problems indicate that a suitable value is n = 50; this implies a value for IWORK of 56. Users are advised to experiment with other values for their own specific problems.

8.3 Convergence

The routine will induce convergence in some divergent sequences. See Shanks [1] for more details.

9 Example

The example program attempts to sum the infinite series

$$\sum_{n=1}^{\infty} \frac{(-1)^{n+1}}{n^2} = \frac{\pi^2}{12}$$

by considering the sequence of partial sums

$$\sum_{n=1}^{1}, \sum_{n=1}^{2}, \sum_{n=1}^{3}, \dots, \sum_{n=1}^{10}$$

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

C06BAF.2 [NP3390/19/pdf]

```
CO6BAF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
     .. Parameters ..
     INTEGER
                    IWORK
                  (IWORK=16)
     PARAMETER
                   NOUT
     INTEGER
     PARAMETER
                    (NOUT=6)
     .. Local Scalars ..
     real ABSERR, ANS, ERROR, PI, R, RESULT, SEQN, SIG
     INTEGER I, IFAIL, NCALL
     .. Local Arrays ..
     real WORK(IWORK)
     .. External Functions ..
     realXO1AAFEXTERNALXO1AAF
     .. External Subroutines ..
     EXTERNAL CO6BAF
     .. Intrinsic Functions ..
     INTRINSIC
                 real
     .. Executable Statements ..
     WRITE (NOUT,*) 'CO6BAF Example Program Results'
     WRITE (NOUT,*)
     PI = X01AAF(0.0e0)
     ANS = PI**2/12.0e0
     NCALL = 0
     SIG = 1.0e0
     SEQN = 0.0e0
     WRITE (NOUT,*)
    + ,
                                          Estimated Actual'
     WRITE (NOUT,*)
    + ' I SEQN
                           RESULT abs error
                                                         error'
     WRITE (NOUT,*)
     DO 20 I = 1, 10
        R = real(I)
        SEQN = SEQN + SIG/(R**2)
        IFAIL = 1
        CALL CO6BAF(SEQN, NCALL, RESULT, ABSERR, WORK, IWORK, IFAIL)
        IF (IFAIL.NE.O) THEN
           WRITE (NOUT, *)
           WRITE (NOUT, 99999) 'CO6BAF fails. IFAIL=', IFAIL
           STOP
        END IF
        ERROR = RESULT - ANS
        SIG = -SIG
        WRITE (NOUT, 99998) I, SEQN, RESULT, ABSERR, ERROR
  20 CONTINUE
     STOP
99999 FORMAT (1X,A,I2)
99998 FORMAT (1X,I4,2F12.4,3X,2e14.2)
     END
```

9.2 Program Data

None.

[NP3390/19/pdf] C06BAF.3

9.3 Program Results

CO6BAF Example Program Results

			Estimated	Actual
I	SEQN	RESULT	abs error	error
1	1.0000	1.0000	0.13+155	0.18E+00
2	0.7500	0.7500	0.13+155	-0.72E-01
3	0.8611	0.8269	0.13+155	0.45E-02
4	0.7986	0.8211	0.26E+00	-0.14E-02
5	0.8386	0.8226	0.78E-01	0.12E-03
6	0.8108	0.8224	0.60E-02	-0.33E-04
7	0.8312	0.8225	0.15E-02	0.35E-05
8	0.8156	0.8225	0.16E-03	-0.85E-06
9	0.8280	0.8225	0.37E-04	0.10E-06
10	0.8180	0.8225	0.45E-05	-0.23E-07

C06BAF.4~(last) [NP3390/19/pdf]