

G02DDF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G02DDF calculates the regression parameters for a general linear regression model. It is intended to be called after G02DCF, G02DEF or G02DFF.

2 Specification

```

SUBROUTINE G02DDF(N, IP, Q, LDQ, RSS, IDF, B, SE, COV, SVD, IRANK,
1                P, TOL, WK, IFAIL)
  INTEGER        N, IP, LDQ, IDF, IRANK, IFAIL
  real          Q(LDQ,IP+1), RSS, B(IP), SE(IP),
1                COV(IP*(IP+1)/2), P(IP*IP+2*IP), TOL,
2                WK(IP*IP+(IP-1)*5)
  LOGICAL        SVD

```

3 Description

A general linear regression model fitted by G02DAF may be adjusted by adding or deleting an observation using G02DCF, adding a new independent variable using G02DEF or deleting an existing independent variable using G02DFF. Alternatively a model may be constructed by a forward selection procedure using G02EEF. These routines compute the vector c and the upper triangular matrix R . G02DDF takes these basic results and computes the regression coefficients, $\hat{\beta}$, their standard errors and their variance-covariance matrix.

If R is of full rank, then $\hat{\beta}$ is the solution to:

$$R\hat{\beta} = c_1, \text{ where } c_1 \text{ is the first } p \text{ elements of } c.$$

If R is not of full rank a solution is obtained by means of a singular value decomposition (SVD) of R ,

$$R = Q_* \begin{pmatrix} D & 0 \\ 0 & 0 \end{pmatrix} P^T.$$

where D is a k by k diagonal matrix with non-zero diagonal elements, k being the rank of R , and Q_* and P are p by p orthogonal matrices. This gives the solution

$$\hat{\beta} = P_1 D^{-1} Q_{*1}^T c_1.$$

P_1 being the first k columns of P , i.e., $P = (P_1 P_0)$ and Q_{*1} being the first k columns of Q_* .

Details of the SVD, are made available, in the form of the matrix P^* :

$$P^* = \begin{pmatrix} D^{-1} P_1^T \\ P_0^T \end{pmatrix}.$$

This will be only one of the possible solutions. Other estimates may be obtained by applying constraints to the parameters. These solutions can be obtained by calling G02DKF after calling G02DDF. Only certain linear combinations of the parameters will have unique estimates, these are known as estimable functions. These can be estimated using G02DNF.

The residual sum of squares required to calculate the standard errors and the variance-covariance matrix can either be input or can be calculated if additional information on c for the whole sample is provided.

4 References

- [1] Golub G H and van Loan C F (1996) *Matrix Computations* Johns Hopkins University Press (3rd Edition), Baltimore

- [2] Hammarling S (1985) The singular value decomposition in multivariate statistics *SIGNUM Newsl.* **20 (3)** 2–25
- [3] Searle S R (1971) *Linear Models* Wiley

5 Parameters

- 1:** N — INTEGER *Input*
On entry: number of observations.
Constraint: $N \geq 1$.
- 2:** IP — INTEGER *Input*
On entry: the number of terms in the regression model, p .
Constraint: $IP \geq 1$.
- 3:** Q(LDQ,IP+1) — *real* array *Input*
On entry: Q must be the array Q as output by G02DCF, G02DEF, G02DFF or G02EEF. If on entry $RSS \leq 0.0$ then all N elements of c are needed. This is provided by routines G02DEF, G02DFF or G02EEF.
- 4:** LDQ — INTEGER *Input*
On entry: the first dimension of the array Q as declared in the (sub)program from which G02DDF is called.
Constraint: $LDQ \geq N$.
- 5:** RSS — *real* *Input/Output*
On entry: either the residual sum of squares or a value less than or equal to 0.0 to indicate that the residual sum of squares is to be calculated by the routine.
On exit: if $RSS \leq 0.0$ on entry, then on exit RSS will contain the residual sum of squares as calculated by G02DDF. If RSS was positive on entry, then it will be unchanged.
- 6:** IDF — INTEGER *Output*
On exit: the degrees of freedom associated with the residual sum of squares.
- 7:** B(IP) — *real* array *Output*
On exit: the estimates of the p parameters, $\hat{\beta}$.
- 8:** SE(IP) — *real* array *Output*
On exit: the standard errors of the p parameters given in B.
- 9:** COV(IP*(IP+1)/2) — *real* array *Output*
On exit: the upper triangular part of the variance-covariance matrix of the p parameter estimates given in B. They are stored packed by column, i.e., the covariance between the parameter estimate given in B(i) and the parameter estimate given in B(j), $j \geq i$, is stored in COV($j \times (j - 1)/2 + i$).
- 10:** SVD — LOGICAL *Output*
On exit: if a singular value decomposition has been performed, then SVD = .TRUE., otherwise SVD = .FALSE..
- 11:** IRANK — INTEGER *Output*
On exit: the rank of the independent variables.
 If SVD = .FALSE., then IRANK = IP.
 If SVD = .TRUE., then IRANK is an estimate of the rank of the independent variables.
- IRANK is calculated as the number of singular values greater than TOL×(largest singular value). It is possible for the SVD to be carried out but IRANK to be returned as IP.

12: P(IP*IP+2*IP) — *real* array

Output

On exit: P contains details of the singular value decomposition if used.

If SVD = .FALSE., P is not referenced.

If SVD = .TRUE., the first IP elements of P will not be referenced, the next IP values contain the singular values. The following $IP \times IP$ values contain the matrix P^* stored by columns.

13: TOL — *real*

Input

On entry: the value of TOL is used to decide if the independent variables are of full rank and, if not, what is the rank of the independent variables. The smaller the value of TOL the stricter the criterion for selecting the singular value decomposition. If TOL = 0.0, then the singular value decomposition will never be used, this may cause run time errors or inaccuracies if the independent variables are not of full rank.

Suggested value: TOL = 0.000001.

Constraint: TOL \geq 0.0.

14: WK(IP*IP+(IP-1)*5) — *real* array

Workspace

15: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, $N < 1$,

or $IP < 1$,

or $LDQ < IP$,

or $LDQ < N$,

or $TOL < 0.0$.

IFAIL = 2

The degrees of freedom for error are less than or equal to 0. In this case the estimates of β are returned but not the standard errors or covariances.

IFAIL = 3

The singular value decomposition, if used, has failed to converge, see F02WEF. This is an unlikely error exit.

7 Accuracy

The accuracy of the results will depend on the accuracy of the input R matrix, which may lose accuracy if a large number of observations or variables have been dropped.

8 Further Comments

None.

9 Example

A data set consisting of 12 observations and four independent variables is input and a regression model fitted by calls to G02DEF. The parameters are then calculated by G02DDF and the results printed.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      G02DDF Example Program Text
*      Mark 14 Release.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          MMAX, NMAX
      PARAMETER        (MMAX=5,NMAX=12)
      INTEGER          NIN, NOUT
      PARAMETER        (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real            RSS, TOL
      INTEGER          I, IDF, IFAIL, IP, IRANK, J, M, N
      LOGICAL          SVD
      CHARACTER        WEIGHT
*      .. Local Arrays ..
      real            B(MMAX), COV(MMAX*(MMAX+1)/2), P(MMAX*(MMAX+2)),
+                   Q(NMAX,MMAX+1), SE(MMAX), WK(MMAX*MMAX+5*MMAX),
+                   WT(NMAX), X(NMAX,MMAX)
*      .. External Subroutines ..
      EXTERNAL         G02DDF, G02DEF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G02DDF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) N, M, WEIGHT
      IF (N.LE.NMAX .AND. M.LT.MMAX) THEN
          IF (WEIGHT.EQ.'W' .OR. WEIGHT.EQ.'w') THEN
              DO 20 I = 1, N
                  READ (NIN,*) (X(I,J),J=1,M), Q(I,1), WT(I)
20             CONTINUE
              ELSE
                  DO 40 I = 1, N
                      READ (NIN,*) (X(I,J),J=1,M), Q(I,1)
40             CONTINUE
              END IF
*      Set tolerance
      TOL = 0.000001e0
      IP = 0
      DO 60 I = 1, M
          IFAIL = -1
*
*      Fit model using G02DEF
      CALL G02DEF(WEIGHT,N,IP,Q,NMAX,P,WT,X(1,I),RSS,TOL,IFAIL)
*
      IF (IFAIL.EQ.0) THEN
          IP = IP + 1
      ELSE IF (IFAIL.EQ.3) THEN
          WRITE (NOUT,*) ' * New variable not added *'
      ELSE
          GO TO 100

```

```

        END IF
60     CONTINUE
        RSS = 0.0e0
        IFAIL = 0
*
        CALL G02DDF(N,IP,Q,NMAX,RSS,IDF,B,SE,COV,SVD,IRANK,P,TOL,WK,
+             IFAIL)
*
        WRITE (NOUT,*)
        IF (SVD) THEN
            WRITE (NOUT,*) 'Model not of full rank'
            WRITE (NOUT,*)
        END IF
        WRITE (NOUT,99999) 'Residual sum of squares = ', RSS
        WRITE (NOUT,99998) 'Degrees of freedom = ', IDF
        WRITE (NOUT,*)
        WRITE (NOUT,*) 'Variable   Parameter estimate   Standard error'
        WRITE (NOUT,*)
        DO 80 J = 1, IP
            WRITE (NOUT,99997) J, B(J), SE(J)
80     CONTINUE
        END IF
100  CONTINUE
        STOP
*
99999 FORMAT (1X,A,e12.4)
99998 FORMAT (1X,A,I4)
99997 FORMAT (1X,I6,2e20.4)
        END

```

9.2 Program Data

G02DDF Example Program Data

```

12 4 'U'
1.0 0.0 0.0 0.0 33.63
0.0 0.0 0.0 1.0 39.62
0.0 1.0 0.0 0.0 38.18
0.0 0.0 1.0 0.0 41.46
0.0 0.0 0.0 1.0 38.02
0.0 1.0 0.0 0.0 35.83
0.0 0.0 0.0 1.0 35.99
1.0 0.0 0.0 0.0 36.58
0.0 0.0 1.0 0.0 42.92
1.0 0.0 0.0 0.0 37.80
0.0 0.0 1.0 0.0 40.43
0.0 1.0 0.0 0.0 37.89

```

9.3 Program Results

G02DDF Example Program Results

Residual sum of squares = 0.2223E+02

Degrees of freedom = 8

Variable	Parameter estimate	Standard error
1	0.3600E+02	0.9623E+00
2	0.3730E+02	0.9623E+00
3	0.4160E+02	0.9623E+00
4	0.3788E+02	0.9623E+00
