

NAG Fortran Library Routine Document

G05LAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G05LAF generates a vector of pseudo-random numbers taken from a Normal (Gaussian) distribution with mean μ and variance σ^2 .

2 Specification

```
SUBROUTINE G05LAF(XMU, VAR, N, X, IGEN, ISEED, IFAIL)
INTEGER          N, IGEN, ISEED(4), IFAIL
real           XMU, VAR, X(*)
```

3 Description

The distribution has PDF (probability distribution function)

$$f(x) = \frac{1}{\sigma\sqrt{2\pi}} \exp\left(-\frac{(x-\mu)^2}{2\sigma^2}\right).$$

The routine uses the Box–Muller method.

One of the initialisation routines G05KBF (for a repeatable sequence if computed sequentially) or G05KCF (for a non-repeatable sequence) must be called prior to the first call to G05LAF.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison-Wesley

Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin

5 Parameters

- | | | |
|----|---|---------------|
| 1: | XMU – <i>real</i>
<i>On entry:</i> the mean, μ , of the distribution. | <i>Input</i> |
| 2: | VAR – <i>real</i>
<i>On entry:</i> the variance, σ^2 , of the distribution.
<i>Constraint:</i> VAR \geq 0.0. | <i>Input</i> |
| 3: | N – INTEGER
<i>On entry:</i> the number, n , of pseudo-random numbers to be generated.
<i>Constraint:</i> N \geq 0. | <i>Input</i> |
| 4: | X(*) – <i>real</i> array
Note: the dimension of the array X must be at least max(1, N).
<i>On exit:</i> the n pseudo-random numbers from the specified Normal distribution. | <i>Output</i> |

- 5: IGEN – INTEGER *Input*
On entry: must contain the identification number for the generator to be used to return a pseudo-random number and should remain unchanged following initialisation by a prior call to one of the routines G05KBF or G05KCF.
- 6: ISEED(4) – INTEGER array *Input/Output*
On entry: contains values which define the current state of the selected generator.
On exit: contains updated values defining the new state of the selected generator.
- 7: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $N < 0$.

IFAIL = 2

On entry, $VAR < 0.0$.

7 Accuracy

The generated numbers conform to a Normal distribution with an accuracy of $\sqrt{\text{machine precision}}$.

8 Further Comments

None.

9 Example

The example program prints 5 pseudo-random numbers from a Normal distribution with mean 1.0 and variance 1.5, generated by a single call to G05LAF, after initialisation by G05KBF.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      G05LAF Example Program Text
*      Mark 20 Release. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER          NOUT, N
      PARAMETER       (NOUT=6,N=5)
*      .. Local Scalars ..
      INTEGER          I, IFAIL, IGEN
```

```
* .. Local Arrays ..
  real X(N)
  INTEGER ISEED(4)
* .. External Subroutines ..
  EXTERNAL G05KBF, G05LAF
* .. Executable Statements ..
  WRITE (NOUT,*) 'G05LAF Example Program Results'
  WRITE (NOUT,*)
* Initialise the seed to a repeatable sequence
  ISEED(1) = 1762543
  ISEED(2) = 9324783
  ISEED(3) = 42344
  ISEED(4) = 742355
* IGEN identifies the stream.
  IGEN = 1
  CALL G05KBF(IGEN, ISEED)
*
  IFAIL = 0
  CALL G05LAF(1.0e0, 1.5e0, N, X, IGEN, ISEED, IFAIL)
*
  WRITE (NOUT, 99999) (X(I), I=1, N)
  STOP
*
99999 FORMAT (1X, F10.4)
END
```

9.2 Program Data

None.

9.3 Program Results

G05LAF Example Program Results

```
3.5652
0.1837
0.9297
-0.6421
0.6371
```
